APPENDIX A

Check if the XDMCP packet is being sent in an allowed direction

35

40

20

55

9

45

10172737.1

Remember the Authentication Names in the user's profile

ELSE IF (the Opcode is Willing) THEN

10172737.1

95

100

105

ELSE IF (the Opcode is Request) THEN IF (the X Display Number is invalid) THEN Discard the packet ENDIF	Remember this Display Number in the user's profile	FOR (each Connection Type in the packet) DO IF (the Connection Type is not IP) THEN Discard the packet ENDIF NEXT	FOR (each Connection Address in the packet) DO IF (the Connection Address is not an IP address) THEN Discard the packet ENDIF	IF (the Connection Address does not match the user's IP address) THEN Replace the Connection Address with the user's IP address ENDIF NEXT	IF (none of the Connection Addresses matched the user's IP address) THEN Discard the packet

110

115

10172737.1

19

IF (the Authentication Name in the packet is not recognized) THEN

ENDIF

Discard the packet ENDIF	IF (the Authentication Name does not match the Authentication Name recorded in the user's profile from the Willing packet) THEN Discard the packet ENDIF	IF (the lengths of the Authentication Name and Authentication Data are not both zero or non-zero) THEN Discard the packet ENDIF	FOR (each Authorization Name in the packet) DO IF (the Authorization Name is not recognized) THEN Discard the packet ENDIF NEXT	Remember the Authorization Names in the user's profile IF (if the Manufacturer Display ID contains invalid characters) THEN Discard the packet ENDIF	IF (if the Manufacturer Display ID does not match any previous recorded Display ID for this user) THEN Discard the packet
120	125	130	135	140	145

ELSE IF (the opcode is Accept) THEN Remember the Session ID in the user's profile	IF (the Authentication Name in the packet is not recognized) THEN Discard the packet ENDIF	IF (the Authentication Name does not match the Authentication Name recorded in the user's profile from the Request packet) THEN Discard the packet ENDIF	IF (the lengths of the Authentication Name and Authentication Data are not both zero or non-zero) THEN Discard the packet ENDIF	IF (the Authorization Name in the packet is not recognized) THEN Discard the packet ENDIF	IF (the Authorization Name does not match any of the Authorization Names recorded in the user's profile from the Request packet) THEN Discard the packet ENDIF	
150	155	160	165	7.70	0/1	1/3

10172737.1

180

185

190

195

10172737.1

205

200

22

ELSE IF (the opcode is Manage) THEN
IF (the Session ID does not match the Session ID recorded in the user's profile from the Accept packet) THEN

Reinitialize the user's profile and set the profile state to Incomplete

Discard the packet

ENDIF

210	IF (the X Display Number is invalid) THEN Discard the packet ENDIF
215	IF (the Display Number does not match the Display Number recorded in the user's profile from the Request packet) THEN Discard the packet ENDIF
220	IF (if the Display Class contains invalid characters) THEN Discard the packet ENDIF
225	IF (if the Display Class does not match any previous recorded Display Class for this user) THEN Discard the packet ENDIF
	Set the user's profile state to Complete
230 ELSE	ELSE IF (the opcode is Refuse) THEN IF (the Session ID does not match the Session ID recorded in the user's profile from the Accept packet) THEN Discard the packet

10172737.1

23

ENDIF

240

ELSE IF (the opcode is Failed) THEN IF (the Session ID does not match the Session ID recorded in the user's profile from the Accept packet) THEN Discard the packet ENDIF	IF (the Status string is NOT composed of printable characters) THEN Discard the packet ENDIF	Reinitialize the user's profile and set the profile state to Incomplete	ELSE IF (the opcode is KeepAlive) THEN IF (the X Display Number is invalid) THEN Discard the packet ENDIF	IF (the Display Number does not match the Display Number recorded in the user's profile from the Manage packet) THEN Discard the packet	IF (the Session ID does not match the Session ID recorded in the user's profile from the Manage packet) THEN Discard the packet ENDIF

250

255

260

245

24

ELSE IF (the opcode is Alive) THEN
IF (the Session Running flag is not 0 or 1) THEN

10172737.1

265	Discard the packet ENDIF
270	IF (the Session Running flag is True) THEN IF (the Session ID does not match the Session ID recorded in the user's profile from the Manage packet) THEN Discard the packet ENDIF
275	ELSE – the Session Running flag is False IF (the Session ID is not zero) THEN Discard the packet ENDIF
280	Reinitialize the user's profile and set the profile state to Incomplete ENDIF
	ELSE – the XDMCP Opcode is not allowed Discard the packet ENDIF
285	ELSE – the XDMCP Opcode is being sent in the wrong direction Discard the packet ENDIF
	ELSE – the XDMCP Opcode is not on the allowed-opcodes list Discard the packet FNDIF
290	ELSE – the server port is not for the XDMCP protocol Discard the packet ENDIF
	ELSE – neither of the IP ports are on the allowed-ports list

10172737.1

10172737.1

56

IF (this is an X-Windows connection) THEN

IF (there is not an existing profile for this user) THEN

325	Discard the packet ELSE – there is an existing profile for this user IF (the state of the user's profile is not Complete) THEN Discard the packet ENDIF
330	IF (the user port does not correspond to the X Display Number in the user's profile) THEN Discard the packet ENDIF
335	ENDIF ENDIF
340	Remember this connection in the user's profile ELSE – the TCP connection is being opened in a disallowed direction Discard the packet ENDIF ELSE – neither of the IP ports are on the allowed-ports list
345	Discard the packet ENDIF ELSE – this is not a TCP SYN packet Discard the packet ENDIF ENDIF
350	Remember the current date/time as that of the last packet on this connection ELSE – it is neither and IP/UDP or IP/TCP packet

10172737.1

Discard the packet

ENDIF ELSE – it is a non-IP packet Discard the packet

ENDIF 355

28

10172737.1